

How to Update W10M Build using Upgrade SPKG/CAB (Without-PC)



Requirements

- ❖ Interop Unlocked W10M Device

Interop Unlock Guides

How to Interop unlock Non-X50 Lumia :



W10M Group



Mega.nz

How to Interop unlock X50 Lumia :



W10M Group



Mega.nz

How to Interop unlock Other OEM :



W10M Group



Mega.nz

THIS GUIDE IS THE "INSTALLATION PART" OF THE "UPGRADE COLLECTION" GUIDES !

How to Collect Upgrade Cabs for each W10M Build :



W10M Group



Mega.nz

Windows 10 Mobile (Lumia) Group :- <https://t.me/Windows10Phone>



Preparations

> Open Settings in your phone, then go to ;

Settings → System → About

Click on **“More Info”**, and take a note of the **“OS Build”** number

Device information
Model: NOKIA Lumia 1520
Software: Windows 10 Mobile
Installed RAM: 2 GB
Version: 1709
OS build: 10.0.15254.603

> If the OS Build is lower than 10.0.14500, Then download 0.0.40.0 version of the Tool ;

IUWP_0.0.40.0 :



W10M Group



Mega.nz



> If the OS Build is higher than 10.0.14500, Then download 0.0.41.0 version of the Tool ;

IUWP_0.0.41.0 :



W10M Group



Mega.nz



> Dependencies if needed

IUWP Dependencies :




W10M Group



Mega.nz


Windows 10 Mobile (Lumia) Group :- <https://t.me/Windows10Phone>




Steps

> Install the correct IUWP version for your W10M Build by following previous Preparation steps.

> Open the IUWP app.




> Now move the folder that includes the cabs of the W10M Build you want to update which you collected using the “How to Backup Upgrade cabs.. Guide” to anywhere in your phone, like to “Downloads” folder.




> Now in IUWP app, go to ;


IU Tasks → Install Packages




> Select **“Browse for Update Cabs”** option to select the folder including the cab files





Windows 10 Mobile (Lumia) Group :- <https://t.me/Windows10Phone>




> Choose the folder and the Cab files should be listed in the app.



> Now click “Install Selected update Packages” to start the installation.




> Then the app should start moving the cabs to update, and when finished, it will start the update and automatically will launch the **"Phone/Windows Update"** page in settings to monitor the installation furthermore.



> It will restart as usual to install the update.

Do the same procedure with every Update you have.



Additional Notes

- Use the correct IUWP version according to your W10M Build.
- Without Interop Unlocking the phone, IUWP app will not Install.
- When Installing Updates, specific cabs for only 1 build, don't mix up 2 builds of cabs or cabs of two phones !

That will cause damage to your phone !

- When updating the phone, Push the update cabs to this order

10.0.10586 → 10.0.14393 → 10.0.15063 → 10.0.15254

BUT :

You can skip Updating to **15063** when you are in **14393**, you can instead push **15254 Upgrade Cabs** to jump from 14393 to 15254 directly.

- You can't downgrade the OS version by pushing older update cab files

Credits

- ✓ Gustave Monce for IUWP app

Thank you for reading.

Have a good day !



Lasitha Samarasinghe

